


Workshop 04.1: Pump with Volute

Release 2020 R2




/ Introduction

- Workshop Description:
 - This Workshop deals with the Fluent setup and solution for Pump
 - The model consists of a pump impeller, connected to a casing (the volute)
- Learning Aims:
 - Setting up a steady stage calculation comprising a rotor and a stator
 - Defining a rotating frame
 - Creating a Frozen Rotor, General Turbo Interface
 - Creating named expressions and report plots for monitoring the head and the power consumption of the pump impeller
 - Solving and monitoring convergence
 - Visualizing the pressure distribution and velocity vectors on a plane of constant axial coordinate




/ Pump Model

- A rotating component (impeller), followed by a stationary component (volute)
 - A moving reference frame is used to solve the rotating component
- Pump data
 - Fluid = Water
 - Speed = 1450 rpm
 - Number of Blades = 6
 - Flow Rate = 77.5 kg/s
 - Axis of rotation = z-axis




/ Start Fluent Launcher

- Start *Fluent Launcher* in *Solution* mode
- Do not check *Double Precision* as the Maximum Aspect Ratio is much smaller than 1000 (see next slide)
- Set the number of Processes for Parallel to 4
 - The mesh size for this case is approximately 1,100,000 cells (see next slide)
 - If you have enough Parallel licenses and more than 4 cores available, you may set up a number of up to 55 Processes (so that each Processor is solving for not less than 20,000 cells)





Fluent

- In the Fluent window read the mesh provided with the workshop inputs
 - File>Read>Mesh
 - Browse to file *centrifugal-pump-volute.msh*
- In the graphics window, you should see the geometry of the pump and volute as shown on the right
 - The mesh comprises the complete impeller and the volute
- Check the mesh size and the mesh quality in the *Mesh* group of the *Domain* tab
 - *Info* > *Size* will give you the number of cells in the *Fluent Console*, which is approximately 1,100,000
 - *Quality* > *Evaluate Mesh Quality* will show you a *Maximum Aspect Ratio* of $1.78e+02 < 1000$
 - This justifies the choice of starting Fluent in Single Precision






For cases with two different mesh files, one for the impeller and one for the volute:

- Read first one mesh file *File>Read>Mesh...*
- When the first mesh is displayed read the second mesh using *Append* in the *Zones* group of the *Domain* tab



Physics: General & Operating Conditions



- Retain the default solver settings of *Pressure-Based* solver with *Absolute Velocity Formulation*



- In the *Operating Conditions* panel set the *Operating Pressure* to 0 (Pa)
 - The pressure difference (inlet to outlet) is expected to be much larger than 1 bar for this case


Physics: Turbulence Model

- Keep the default *SST k-omega Viscous Model*
- The *SST k-omega model* (default *Viscous Model* starting with 2020 R1) is the recommended turbulence model for turbomachinery simulations





Physics: Materials

- Make Water material available:
 - From the *Fluent Database...* select water-liquid(h2o<l>) and click *Copy* and *Close*
 - Click *Change/Create* and close the *Create/Edit Materials* dialog box




Create a Named Expression for Rotational Speed

- The pump impeller is rotating with a rotational speed of 1450 rpm
- We will need to set this in the conditions for the *impeller* cell zone (see next slide)
- We are going to use a *Named Expression* for this
- In the *Outline*, RMB on *Named Expressions* and select *New...*
- In the *Expression* panel:
 - enter *omega* under *Name*,
 - *1450 [rev/min]* under *Definition*
 - Click *OK*





Physics: Cell Zone Conditions

- Edit the *impeller* cell zone
 - Select *water-liquid* as *Material Name*
 - Enable *Frame Motion*
 - The default *Rotation-Axis Direction* is the z-axis and is suitable for this case
 - Using the drop-down list next to *Speed* under *Rotational Velocity*, set this to *expression*
 - In the box next to *Speed*, type *omega* (i.e., the name of the expression created in the previous slide)
 - After typing the first few letters of *omega*, you will see that the name *omega* is highlighted in a blue box. You may left-click on it to select it, or continue typing the complete expression name



Physics: Cell Zone Conditions (2)

- Continuing from previous slide...
- The settings of cell zone *impeller* should look as in the right-top image
- Click *Apply*
- The rotational speed has been set via an expression $\omega = 1450 \text{ [rev/min]}$
 - Sign verification: If you place your right thumb to point as the positive z-axis, your fingers are curling (in this case) to the same direction with the rotation direction of the impeller. Therefore, the Rotational Velocity was set to a positive number
- Expressions are used for a consistent setup and may also be used for the calculation of key targeted quantities
 - ω will be later used, in conjunction with a Force report for the moment, for creating a report for the impeller power




Physics: Cell Zone Conditions (3)

- Edit the *volute* cell zone
 - Select *water-liquid* as *Material Name*
 - Click *Apply*

The screenshot shows the 'Fluid' dialog box for editing the 'volute' cell zone. The 'Zone Name' field contains 'volute'. The 'Material Name' dropdown menu is highlighted with a red box and shows 'water-liquid' selected. To the right of the dropdown is an 'Edit...' button. Below these are several unchecked checkboxes: 'Frame Motion', '3D Fan Zone', 'Source Terms', 'Mesh Motion', 'Laminar Zone', 'Fixed Values', and 'Porous Zone'. A row of tabs is visible: 'Reference Frame' (selected), 'Mesh Motion', 'Porous Zone', '3D Fan Zone', 'Embedded LES', 'Reaction', 'Source Terms', 'Fixed Values', and 'Multiphase'. The 'Reference Frame' tab is active, showing two sections: 'Rotation-Axis Origin' and 'Rotation-Axis Direction'. The 'Rotation-Axis Origin' section has three input fields: 'X (m)' with value 0, 'Y (m)' with value 0, and 'Z (m)' with value 0. The 'Rotation-Axis Direction' section has three input fields: 'X' with value 0, 'Y' with value 0, and 'Z' with value 1. At the bottom right are three buttons: 'Apply', 'Close', and 'Help'.



Boundary Conditions: Inlet

- Set the boundary conditions for *impeller-inlet*
 - RMB on *impeller-inlet* and set *Type* to *pressure-inlet*
 - Check *Prevent Reverse Flow*
 - Set a *Gauge Total Pressure* of 100000 (pascal) at the inlet *
 - Set a *Supersonic/Initial Gauge Pressure* of 98000 (pascal)
 - *Initial Gauge Pressure* is set a few (pascal) lower than the *Gauge Total Pressure*. This will help in the flow field initialization (see slide 24)
 - Accept all remaining defaults in the Momentum tab
 - Click *Apply*
- * Note that the Operating Pressure was set to 0 (Pa) for this case. For this reason, the inlet Gauge Total Pressure is set to 100000 (Pa)






Boundary Conditions: Outlet

- Set the boundary conditions for *volute-outlet*
 - RMB on *volute-outlet* and set *Type* to *mass-flow-outlet*
 - Set the *Mass Flow Rate* = $77.5(\text{kg/s})$
 - Click *Apply*





Boundary Conditions: Automatically Set Walls

- From the remaining zones under *Wall* in the *Outline View*, all boundaries correspond to walls, which can be left to the default wall boundary condition setting:
 - *Stationary Wall*
 - *Relative to Adjacent Cell Zone*
 - *No Slip*





Define a Frozen Rotor Interface

- Having concluded with all basic boundary conditions, you will now define a *Frozen Rotor General Turbo Interface*
 - In the *Domain* tab under *Turbo Model* group check *Enable* and click *Turbo Create...*
 - In the *Create/Edit Turbo Interfaces* panel:
 - Set mesh interface name to *impeller-to-volute*
 - Check *General Turbo Interface*
 - Select the two sides of the interface
 - Select *No Pitch-Scale*
 - Click *Create/Edit*
 - Ignore any error message in the console after clicking *Create/Edit*
 - Do a mesh check and make sure that no error message appears in the console



Solution: Moment Report Definition

- In the *Solution* tab create a new *Force Report Definition* for the *Moment* about the *z-axis*, with the following settings:
 - *Name* = *moment*
 - *Report Output Type* = *Moment*
 - *Boundaries* = *all 3 impeller walls*
 - *Report File* = *checked*
 - *Report Plot* = *checked*
 - *Moment Axis* → keep the default corresponding to the z-axis)
 - Click *OK*




New Method for Report Definitions Using Named Expressions

- You will now use a new method for creating Report Definitions and Output Parameters, based on Named Expressions
 - Named Expressions are introduced in the Fluent Getting Started course in the “Setting up Physics” lecture
 - In this workshop for convenience, a file *PumpVolute.tsv* is provided with the workshop inputs, containing the syntax for 5 named Expressions:

name	definition	description	input-parameter	output-parameter
"ave_ptot_in"	"Average(TotalPressure,['impeller-inlet'],Weight = 'MassFlowRate')"	""	#f	#f
"ave_ptot_out"	"Average(TotalPressure,['volute-outlet'],Weight = 'MassFlowRate')"	""	#f	#f
"deltapt"	"ave_ptot_out-ave_ptot_in"	""	#f	#f
"den"	"998.2 [kg_m^-3]"	""	#f	#f
"head"	"deltapt/(den*g)"	""	#f	#f



You can import this file into the *Named Expressions* branch of the *Outline* using *RMB>Import From File...*

- The 5 *Named Expressions* highlighted by a red box in the bottom-right image are created





New Method for Report Definitions Using Named Expressions (2)

- Double click on any of the new *Named Expressions* for examining its definition in the *Expression* editor




Solution: Create Report Definitions Using Named Expressions

- In the *Solution* tab click on *Definitions* in the *Reports* section and choose *New > Expression...*
Enter the following in the definition panel and click *OK*:
 - *Name* = *head*
 - *Expressions* > *head*
 - *Report File* = checked
 - *Report Plot* = checked





Solution: Create Report Definition for the Pump Power

- In the *Solution* tab click on *Definitions* in the *Reports* section and choose *New >Expression...*
Enter the following in the definition panel and click *OK*:
 - Name = *power*
 - $\{moment\} * \omega$
 - This expression can be typed directly in the expression definition box, or one can use the drop-down lists of existing *Expressions* for *omega* and *Report Definitions* for *moment*
 - Report File = checked
 - Report Plot = checked



/ Solution: Solution Methods





- Always use the default *Coupled “Pseudo-Transient” Solver* for turbomachinery calculations
 - If for any reason the Solution method is set to some *Scheme* other than *Coupled*, click the *Default* button at the bottom of the panel
- Turn on *High Order Term Relaxation* (more stable)



Solution: Initialization (Best Practice Procedure)


- Perform a *Standard Initialization* using the inlet values
 - Remember we have set the *Initial Gauge Pressure*, a bit lower than the *Gauge Total Pressure* (slide 14)
 - This will ensure a proper k and omega initialization
- Then perform a *Hybrid Initialization*, after having checked the option *Use Specific Initial Pressure on Inlets*
- Save a Fluent .cas and .dat file
 - *File > write > Case & Data...*

Note: FMG initialization is currently not compatible with all General Turbo Interfaces




/ Solution: Run the Solver

- Click on *Run Calculation...*
 - Set *Verbosity* to 1
 - This will produce a more detailed runtime solver output, including the time step used by the pseudo-transient solver
- Set *Time Scale Factor* to 10
- Set *No. of Iterations* to 250
- Click *Calculate*




/ Solver Convergence

- The case does not converge well to a steady state solution after 250 iterations
 - Residual for continuity drops by 2 orders of magnitude
 - All rest residuals drop to values close to, or less than $1e-03$
 - Residuals and report plots show a bouncy behavior




/ Check Solver Convergence Further

- It is a good idea to do a more detailed check of residuals and monitors.
To do this:
 - Clear all *Report-Plots* data
 - This can be done by expanding the *Monitors* branch in the *Outline* and *RMB* > *Clear Data* for each *Report Plot*
 - This will reset the x- and y-axes limits of the report plots (see next slide)
 - Click *Calculate* in the *Solution* tab in the ribbon, for performing more solver iterations




Solver Convergence

- Residuals and report plots show a bouncy behavior
 - Case is not converging to a steady state
 - Continuity residuals oscillate around $1e-2$ and cannot be reduced further
 - The targeted quantities of *head* and *power* seem to be constant within 2-3 significant figures
 - *head* ≈ 21.3 (m)
 - *power* ≈ -20200 (watt)
 - To check the accuracy of these key quantities, it is a good idea to investigate the case by solving it also as transient






Note: Residuals and monitor plots may differ between two computers or Ansys releases






Create a Surface of Constant Axial Coordinate

- Create an *Iso-Surface* of $z\text{-Coordinate} = -0.02\text{ m}$



Pressure Contours on Surface $z=-0.02$


- Create a *New Contour* plot of *Static Pressure* on surface $z=-0.02$



Note: Results may differ between two computers or Ansys releases




Define Reference Zone for Relative Velocities

- In the *Reference Values* panel set the *Reference Zone* to *impeller*
 - In this model, we have one moving and one stationary fluid zone. The *Reference Zone* determines how the relative velocities are computed. See lecture 03 on Post-processing for more details



Velocity Vectors on Surface $z=-0.02$


- Create a *New Vector* plot of *Velocity* on Surface $z=-0.02$





Note: Results may differ between two computers or Ansys releases

Relative Velocity Vectors on Iso-surface $z=-0.02$

- Create a *New Vector* plot of *Relative Velocity* on Surface $z=-0.02$



- Write the Fluent .cas and .dat files and exit Fluent



Note that you will have to set the *Reference Zone* as described on slide 30 and might also have to perform one more solver iteration, so that the relative velocity vectors look like the ones in the image here.

/ Summary

- This workshop has covered:
 - Setting up a steady stage calculation comprising a rotor and a stator
 - Defining a rotating frame
 - Creating a Frozen Rotor, General Turbo Interface
 - Creating named expressions and report plots for monitoring the head and the power consumption of the pump impeller
 - Solving and monitoring convergence
 - Visualizing the pressure distribution and velocity vectors on a plane of constant axial coordinate



End of presentation